



Human Pulmonary Alveolar Epithelial Cells (HPAEpiC)

Catalog Number: 3200

Cell Specification

Pulmonary alveolar epithelial cells (PAEpiC) comprised of alveolar type I and type II epithelial cells, line more than 99% of the internal surface area of the lung [1]. Type I cells are large squamous cells whose thin cytoplasmic extensions cover >95% of the internal surface area. They contain aquaporins and exhibit the highest osmotic water permeability of any mammalian cell type. Type II cells, which cover 2-5% of the surface area, produce, secrete, and recycle pulmonary surfactant [2]. Type II cells contain Na^+ , K^+ -ATPase and amiloride-sensitive epithelial Na^+ channels. The currently accepted hypothesis is that Type II cells maintain pulmonary fluid homeostasis by regulating active Na^+ transport in the lungs, whereas Type I cells are "inert" cells that provide solely a barrier function, rather than having active functions. Recent study indicate that Type I cells are also important in regulating ion and fluid transport [3].

HPAEpiC from ScienCell Research Laboratories are isolated from human lung tissue. HPAEpiC are cryopreserved at primary culture and delivered frozen. Each vial contains $>1 \times 10^6$ cells in 1 ml volume. HPAEpiC are characterized by immunofluorescent method with antibodies CK-18, -19, and vimentin. HPAEpiC are negative for HIV-1, HBV, HCV, mycoplasma, bacteria, yeast and fungi. HPAEpiC are guaranteed to further culture at the conditions provided by ScienCell Research Laboratories. *However, this cell type is not recommend for expanding or long term cultures since the cells would differentiate to become type I alveolar epithelial cells immediately after plating and type I alveolar epithelial cells do not proliferate in culture.*

Recommended Medium

It is recommended to use Alveolar Epithelial Cell Medium (AEpiCM, Cat. No. 3201) for the culturing of HPAEpiC *in vitro*.

Product Use

HPAEpiC are for research use only. It is not approved for human or animal use, or for application in *in vitro* diagnostic procedures.

Storage

Directly and immediately transfer cells from dry ice to liquid nitrogen upon receiving and keep the cells in liquid nitrogen until cell culture needed for experiments.

Shipping

Dry ice.

Reference

- [1] Crapo, J. D., Young, S. L., Fram, E. K., Pinkerton, K. E., Barry, B. E., & Crapo, R. O. (1983) Morphometric characteristics of cells in the alveolar region of mammalian lungs. *Am. Rev. Respir. Dis.* 128:S42-S46.
- [2] Wright, J. R. & Dobbs, L. G. (1991) Regulation of pulmonary surfactant secretion and clearance. *Annu. Rev. Physiol.* 53:395-414.
- [3] Johnson, M. D., Widdicombe, J. H., Allen, L., Barbry, P. and Dobbs, L. G. (2002) Alveolar epithelial type I cells contain transport proteins and transport sodium, supporting an active role for type I cells in regulation of lung liquid homeostasis *Proc. Natl. Acad. Sci. USA.* 99(4):1966-1971.

Instruction for culturing cells

Caution: Cryopreserved cells are very delicate. Thaw the vial in a 37°C waterbath and return them to culture as quickly as possible with minimal handling!

Set up culture after receiving the order:

1. Prepare a poly-L-lysine coated flask (2 $\mu\text{g}/\text{cm}^2$, T-75 flask is recommended). Add 10 ml of sterile water to a T-75 flask and then add 15 μl of poly-L-lysine stock solution (10 mg/ml, ScienCell cat. no. 0413). Leave the flask in incubator overnight (minimum one hour at 37°C incubator).
2. Prepare complete medium: decontaminate the external surfaces of medium and medium supplements with 70% ethanol and transfer them to sterile field. Aseptically open each supplement tube and add them to the basal medium with a pipette. Rinse each tube with medium to recover the entire volume.
3. Rinse the poly-L-lysine coated flask with sterile water twice and add 20 ml of complete medium to the flask. Leave the flask in the hood and go to thaw the cells.
4. Place the vial in a 37°C waterbath, hold and rotate the vial gently until the contents are completely thawed. Remove the vial from the waterbath immediately, wipe it dry, rinse the vial with 70% ethanol and transfer it to a sterile field. Remove the cap, being careful not to touch the interior threads with fingers. Using a 1 ml eppendorf pipette gently re-suspend the contents of the vial.
5. Dispense the contents of the vial into the equilibrated, poly-L-lysine coated culture vessels. A seeding density of 5,000 cells/ cm^2 is recommended.

Note: Dilution and centrifugation of cells after thawing are not recommended since these actions are more harmful to the cells than the effect of DMSO residue in the culture. It is also important that cells are plated in poly-L-lysine coated flask that promotes cell attachment.

6. Replace the cap or cover, and gently rock the vessel to distribute the cells evenly. Loosen cap if necessary to permit gas exchange.
7. Return the culture vessels to the incubator.
8. For best result, do not disturb the culture for at least 16 hours after the culture has been initiated. Change the growth medium the next day to remove the residual DMSO and unattached cells, then every other day thereafter. A health culture will display polygonal shaped, sheets of contiguous cells and the cell number will be double after two to three days in culture.

Maintenance of Culture:

1. Change the medium to fresh supplemented medium the next morning after establishing a culture from cryopreserved cells.
2. Change the medium every three days thereafter, until the culture is approximately 70% confluent.
3. Once the culture reaches 70% confluence, change medium every other day until the culture is approximately 90% confluent.

Subculture:

The purpose of subculture is not for expanding cells, rather to transfer cells to specific devices such as 6-well insert for studying the property of cells

1. Subculture the cells when they are over 90% confluent.
2. Prepare poly-L-lysine coated cell culture flasks ($2\ \mu\text{g}/\text{cm}^2$).
3. Warm medium, trypsin/EDTA solution (T/E, cat. no. 0103), trypsin neutralization solution (TNS, cat. no. 0113), and DPBS (Ca^{++} and Mg^{++} free, cat. no. 0303) to **room temperature**. We do not recommend warming the reagents and medium at 37°C waterbath prior to use.
4. Rinse the cells with DPBS.
5. Add 7 ml of DPBS first and then 3 ml of trypsin/EDTA solution into flask (in the case of T-75 flask); gently rock the flask to make sure cells are covered by trypsin/EDTA solution; incubate the flask at 37°C incubator for 1 to 3 minutes or until cells are completely rounded up (monitored with inverted microscope). During incubation, prepare a 50 ml conical centrifuge tube with 5 ml of fetal bovine serum (FBS, cat. no. 0500); transfer trypsin/EDTA solution from the flask to the 50 ml centrifuge tube (a few percent of cells may detached); continue incubate the flask at 37°C for 1 or 2 minutes more (no solution in the flask at this moment); at the end of trypsinization, one hand hold one side of flask and the other hand gently tap the other side of the flask to detach cells from attachment; check the flask under inverted microscope to make sure all cells are detached, add 5 ml of trypsin neutralization solution to the flask and transfer detached cells to the 50 ml centrifuge tube; add another 5 ml of TNS to harvest the residue cells and transfer it to the 50 ml centrifuge tube. Examine the flask under inverted microscope to make sure the cell harvesting is successful by looking at the number of cells left behind. There should be less than 5%.

Note: Use ScienCell Research Laboratories' trypsin/EDTA solution that is optimized to minimize the killing of the cells by over trypsinization.

6. Centrifuge the 50 ml centrifuge tube (harvested cell suspension) at 1000 rpm (*Beckman Coulter Allegra 6R* centrifuge or similar) for 5 min; re-suspend cells in growth medium.

7. Count cells and plate cells in a new, poly-L-lysine coated flask with cell density as recommended.

Caution: Handling human derived products is potentially biohazardous. Although each cell strain tests negative for HIV, HBV and HCV DNA, diagnostic tests are not necessarily 100% accurate, therefore, proper precautions must be taken to avoid inadvertent exposure. Always wear gloves and safety glasses when working these materials. Never mouth pipette. We recommend following the universal procedures for handling products of human origin as the minimum precaution against contamination [1].

[1]. Grizzle, W. E., and Polt, S. S. (1988) Guidelines to avoid personal contamination by infective agents in research laboratories that use human tissues. J Tissue Culture Methods. 11(4).